


EXHIBIT 8

Ser. No.: 10/005,728

42390P5943C



☒ The intellisense upgrade for Visual Studio .NET - make your IDE as smart as you.

All Topics, MFC / C++ >> System >> General

Get the Processor Speed in two simple ways

By Thomas Latuske

C++ (VC6)
Windows (NT4, WinXP)
Win32, VS, MFC
Dev
Posted 8 Jun 2004
Updated 13 Jun 2004
Articles by this author
7,845 views

Get the frequency of the processor either from the registry, or calculate it.

Search: Articles ☒ ☐

Help! Articles Message Boards StoreFront Lounge

25 members have rated this article. Result:

Popularity: 6.5. Rating: 4.65

Toolbox

Broken Article?

VS.NET 2003 for \$899

MSDN Univ. from \$1950

Print version

Send to a friend

Sign in / Sign up


Email

Password

☒ Remember me

Lost your Password?

- Download demo project - 20.8 Kb



Introduction

I'll show you two ways to retrieve the processor-speed (**frequency in MHz**). W simple functions, one to retrieve the frequency from the registry of your Windo operating system, and one to calculate it with the clock cycles and a high resolu counter. If you want to use the function to calculate the speed (**frequency**), yc to use it with a Pentium Instruction set compatible processor (look at the lines t

rfmobile wrote in a message:

You don't need to change the RDTSC definition for non-Intel processors. The code works as-is on my AMD mobile Athlon. Should work on any Pentium instruction set compatible processor but not for 486 or 386.

I'm not able to verify this, so I would like to hear some feedback.

BTW: **Constructive** criticism is always welcome! :-)

file://C:\Work\Patents\Applications%20Pending\P5943C\Declaration%201.132%20evide... 10/11/2004

Routine to retrieve the speed (frequency) from the reg

This is plain code to retrieve a registry value as a CString:

```
CString ProcSpeedRead()
{
    CString sMHz;
    char Buffer[_MAX_PATH];
    DWORD BufSize = _MAX_PATH;
    DWORD dwMHz = _MAX_PATH;
    HKEY hKey;

    // open the key where the proc speed is hidden:
    long lError = RegOpenKeyEx(HKEY_LOCAL_MACHINE,
        "HARDWARE\\DESCRIPTION\\System\\CentralProcessor\\",
        0,
        KEY_READ,
        &hKey);

    if(lError != ERROR_SUCCESS)
    {
        // if the key is not found, tell the user why:
        FormatMessage(FORMAT_MESSAGE_FROM_SYSTEM,
            NULL,
            lError,
            0,
            Buffer,
            _MAX_PATH,
            0);
        AfxMessageBox(Buffer);
        return "N/A";
    }

    // query the key:
    RegQueryValueEx(hKey, "-MHz", NULL, NULL, (LPBYTE) &dwMHz, &BufSi

    // convert the DWORD to a CString:
    sMHz.Format("%i", dwMHz);

    return sMHz;
}
```

Routine to calculate the processor frequency in MHz:

Retrieve the frequency in MHz as a floating-point number. I use some well documented (at least for me ;-)) assembler here:

```
float CGettheProcessorSpeedDlg::ProcSpeedCalc()
{
    /*
    RdTSC:
    It's the Pentium instruction "Read Time Stamp Counter". It measures the
    number of clock cycles that have passed since the processor was reset, as
    64-bit number. That's what the <CODE>_emit lines do.*/
    #define RdTSC __asm __emit 0x0f __asm __emit 0x31

    // variables for the clock-cycles:
    __int64 cyclesStart = 0, cyclesStop = 0;
    // variables for the High-Res Performance Counter:
    unsigned __int64 nCtr = 0, nFreq = 0, nCtrStop = 0;
```

```

// retrieve performance-counter frequency per second:
if(!QueryPerformanceFrequency((LARGE_INTEGER *) &nFreq)) return 0;

// retrieve the current value of the performance counter:
QueryPerformanceCounter((LARGE_INTEGER *) &nCtrStop);

// add the frequency to the counter-value:
nCtrStop += nFreq;

_asm
{
    // retrieve the clock-cycles for the start value:
    RDTSC
    mov DWORD PTR cyclesStart, eax
    mov DWORD PTR [cyclesStart + 4], edx
}

do{
    // retrieve the value of the performance counter
    // until 1 sec has gone by:
    QueryPerformanceCounter((LARGE_INTEGER *) &nCtr);
}while (nCtr < nCtrStop);

_asm
{
    // retrieve again the clock-cycles after 1 sec. has gone by:
    RDTSC
    mov DWORD PTR cyclesStop, eax
    mov DWORD PTR [cyclesStop + 4], edx
}

// stop-start is speed in Hz divided by 1,000,000 is speed in MHz
return ((float)cyclesStop-(float)cyclesStart) / 1000000;
}

```

Credits

- I got the assembler some time ago from an assembler newsgroup
- ...and credits to all programmers out there who share their knowing!

About Thomas Latuske



My name is Thomas, I'm born on January the 11th in 1970, right now I'm working in the Quality department of a big Pipe mill as a Technician. My hobbies are my girl friend, my car, RC-Planes and Computers. I begun with VC++ some time ago and now Programming is like a drug to me (I'm still a beginner). I want to learn it all in a blink of an eye 😊 but i know that this is not possible. It's real fun for me and I do small Programms for my own use. O.K. enough written..... I need my Time to debug everything that crosses my way! 😊

Click here to view **Thomas Latuske's** online profile.

Other popular System articles:

- **API hooking revealed**
The article demonstrates how to build a user mode Win32 API spying system
- **Using MC.exe, message resources and the NT event log in your own projects**
A tutorial that shows how to integrate mc.exe in the build environment of VisualStudio and use it for event logging and string resources
- **Serial library for C++**
A high-performance, complete and compact serial library for C++
- **System Dialogs**
This article shows you a very simple way to show system dialogs like Internet Options, Add/Remove Programs, and etc.

[\[Top\]](#)
Sign in to vote for this article: *Poor* ○ ○ ○ ○ ○ *Excellent*

<input checked="" type="checkbox"/> MSDN Magazine - Your guide to Microsoft tools, development	<input checked="" type="checkbox"/> The intellisense upgrade for Visual Studio .NET - make your IDE as smart as you
---	---

Premium Sponsor



FAQ

Noise level

Search comments

View Per page
New thread

Msgs 1 to 15 of 15 (Total: 15) (Refresh)

Subject	Author	Date
Why waiting that second?	Anonymous	5:58 29 Jul '04
Accuracy not guaranteed	DavidCrow	14:05 17 Jun '04
The code I'm posting here has always worked for me	Olan Patrick Barnes	15:14 14 Jun '04
Re: The code I'm posting here has always worked for me	Thomas Latuske	16:39 14 Jun '04
Get Processor Speed should be Get Processor Frequency	technomanceraus	1:30 9 Jun '04
Re: Get Processor Speed should be Get Processor Frequency	RichardGrimmer	10:18 9 Jun '04
Re: Get Processor Speed should be Get Processor Frequency	Anonymous	23:21 13 Jun '04
Re: Get Processor Speed should be Get Processor Frequency	Vince C.	4:22 15 Jun '04
RDTS	rfmobile	21:07 8 Jun '04
Re: RDTS	Thomas Latuske	12:04 13 Jun '04
Registry method works only on NT	dacris	15:39 8 Jun '04
Re: Registry method works only on NT	Rick York	16:04 8 Jun '04
Re: Registry method works only on NT	Thomas Latuske	16:43 8 Jun '04
Code will break soon...	DiWa	14:08 8 Jun '04

file://C:\Work\Patents\Applications%20Pending\P5943C\Declaration%201.132%20evid... 10/11/2004

The Code Project - Get the Processor Speed in two simple ways - System

Page 5 of 5

 Re: Code will break soon... Thomas Latuske

15:04 8 Jun '04

Last Visit: 19:25 Wednesday 6th October, 2004

[First](#) [Prev](#) [Next](#) [Last](#)All Topics, MFC / C++ >> System >> General
Updated: 13 Jun 2004Article content copyright Thomas Latuske, 2004
everything else Copyright © CodeProject, 1999-2004.
[Advertise on The Code Project](#) | [Privacy](#)[MSDN Communities](#) | [ASPAlliance](#) • [Developer Fusion](#) • [DevGuru](#) • [Programmers Heaven](#) • [Planet Source Code](#) • [Resource Index](#) • [Tek-Tips Forums](#) • [What is XML?](#) • [VisualBuilder](#) • [ZVON](#) • [Search Us!](#)

file:///C:/Work/Patents/Applications%20Pending/P5943C/Declaration%201.132%20evid... 10/11/2004